InChl version 1, Software version 1.06

User's Guide

Last revision date: December 15, 2020

User's Guide

I. OVERVIEW

About InChl
Standard and non-standard InChl
About InChlKey

II. ABOUT InChI PROGRAMS

III. RUNNING InChi PROGRAMS

Command Line Executable inchi-1 InChI Software Library (libinchi) Graphical Interface Program (winchi-1) InChI Software Options

IV. CHEMICAL STRUCTURE INPUT

V. Further reading and contacts

This introductory User Guide is addressed to the novice user of InChI whose primary interest is to learn how to produce InChI/InChIKey identifiers of chemical compounds with InChI executables included in InChI Software distribution (note that alternatively one may simply use nearly any chemical drawing programs as, at the moment of this writing, they typically have a built-in InChI generation ability).

I. OVERVIEW

About InChl

The IUPAC International Chemical Identifier (InChI) provides unique labels for well-defined chemical substances. These labels are generated by converting an input chemical structure, in the form of a 'connection table', to a unique and predictable series of ASCII characters. They offer a means for representing chemical compounds in a manner that does not depend on how they were drawn. Note that they are re-expressions of chemical structures, they are not registry or registration numbers and do not require access to a database. They were developed primarily as a means of 'naming' a compound in digital media although they are expressed as simple text that may be manually interpreted. This document describes the operation and output of the present version of the program that generates this Identifier.

The Identifier is designed to process single, well-defined chemical compounds (which may be composed of multiple components).

InChI is a project of the International Union of Pure and Applied Chemistry (IUPAC) described at: http://www.iupac.org/inchi/

The IUPAC body which takes care of the current and future shape of InChI is the "IUPAC InChI Subcommittee" (IUPAC Division VIII InChI Subcommittee), which reports to IUPAC Division VIII and also to the IUPAC Committee on Publications and Cheminformatics Data Standards. There exist also InChI Subcommittee working groups made up of additional chemists who are developing

rules for extending the capabilities of InChI. See: http://iupac.org/web/ins/802

Historically, the primary development of the InChI algorithm and software took place at NIST (US National Institute of Standards and Technology, USA) under the auspices of IUPAC. Since 2009, the responsibility for InChI technical development and promotion has been in the hands of the InChI Trust (http://www.inchi-trust.org/) – a not-for-profit organization which works in close contact with IUPAC (and of which IUPAC is a member).

Technical details are given in a separate document, the InChI Technical Manual. The basic algorithms were taken from the literature, with selection, testing and implementation done primarily at NIST; with modifications and additions by IUPAC and the InChI Trust.

In the several years of its development, many individuals contributed to the development of the InChI at meetings and through correspondence. The chemical rules employed are intended to represent a consensus view of the concept of chemical identity. The computer program described in this document applies these algorithms to input structures and generates both the Identifier and an annotated depiction of the structure.

Derivation of the InChI from an input chemical structure proceeds through three steps:

1) normalization – all input information not needed for structure identification is discarded and structure information is divided into 'layers'; 2) canonicalization – each atom is given a label that depends only on its position in the structure; 3) serialization – a string of characters, the Identifier, is generated from the canonical labels. All 'chemical' rules are applied in the first step.

The current version of InChI Identifier is 1; the current stable version of the InChI software is 1.06 which replaces the previous version 1.05.

Standard and non-standard InChl

InChI has a layered structure which allows one to represent molecular structure with a desired level of detail. Accordingly, the InChI Software may generate different InChI strings for the same molecule, depending on the choice of a multitude of options (e.g., distinguishing or not distinguishing tautomers). This flexibility, however, may be considered a drawback with respect to standardization/interoperability. The standard InChI which is always produced with fixed options was defined by the IUPAC InChI Subcommittee in response to these concerns.

The standard InChI was defined to ensure interoperability/compatibility between large databases/web searching and information exchange. As related to its internal layered structure, standard InChI, introduced in v.1.02-standard (2009) release of InChI Software, is a subset of IUPAC International Chemical Identifier v.1. The layered structure of the standard InChI conforms to the following requirements.

- \cdot Standard InChI organometallic representation does not include bonds to metal for the time being.
- Standard InChI distinguishes between chemical substances at the level of 'connectivity', 'stereochemistry', and 'isotopic composition', where:

§ connectivity means tautomer-invariant valence-bond connectivity (different tautomers have the same connectivity/hydrogen layer);

§ stereochemistry means configuration of stereogenic atoms and bonds; unknown stereo designations are treated as undefined;

§ isotopic composition means mass numbers of isotopic atoms (when specified)

Standard InChl v.1 was introduced in v. 1.02-standard release of the InChl Software in 2009 (this software version was able of generating only standard InChls).

The present release of InChI Software, v. 1.06, has merged functionality. It allows one to produce both standard and non-standard InChI strings, as well as their hashed representation (InChIKey).

By default, InChI Software v. 1.06 produces standard InChI (for brevity, stdInChI below). In particular, the standard identifier is generated when the software is used without any specifically added options. If some options are specified, and at least one of them qualifies as related to non-standard InChI (see section 'InChI Software Options' below), the program produces non-stdInChI/InChIKey.

The standard InChI is designated by the prefix: "InChI=1S/......" (that is, letter 'S' immediately follows the Identifier version number, '1'; Identifier version numbers should always be whole numbers).

Non-standard InChl is designated by the prefix: "InChl=1/..........." (that is, letter 'S' is omitted).

InChl's obtained with the experimental features of the Software (support of polymers; support of "large" molecules) are designated by the prefix: InChl=1B/......('B' for beta).

About InChlKey

The InChIKey is a character signature based on a hash code of the InChI string. A hash code is a fixed length condensed digital representation of a variable length character string. Providing a hash derived from an InChI string should be helpful in search applications, including Web searching and chemical structure database indexing; also, this hash may serve as a checksum for verifying InChI, for example, after transmission over a network.

The InChlKey consists of two blocks. The first block is always the same for the same molecular skeleton. All isotopic substitutions, changes in stereoconfiguration, tautomerism and protonation are reflected in the second block.

A standard InChIKey, which is a key produced from a standard InChI, does not account for tautomerism and may indicate only absolute stereo (or completely ignore stereo). It also does not account for the original structure's bonds to metal.

The two hash blocks of InChlKey are based on a truncated SHA-256 cryptographic hash function.

Note that due to the very essence of hashing, appearance of collisions (the same InChIKey for different InChIs/structures) is unavoidable in very large collections. A theoretical – optimistic – estimate of collision resistance is as follows. The probability of a single first block collision in a database of 1 billion compounds is 1.3%. In other words, a single first block collision is expected in 1 out of 100/1.3 = 75 databases of 10^9 compounds each. For 10^8 (100 million) compounds in a database this probability is 0.014%.

For more details, please refer to the dedicated paper:

I. Pletnev, A. Erin, A. McNaught, K. Blinov, D. Tchekhovskoi, and S. Heller. InChlKey collision resistance: an experimental testing. Journal of Cheminformatics, 4:39–39, 2012. DOI: 10.1186/1758-2946-4-39.

A beta-version of the InChlKey was introduced in software v. 1.02-beta (2007). The standard InChlKey was introduced in v. 1.02-standard release (2009) as an InChlKey computed from the standard InChl and intended for the principal purpose of a search-engine-style lookup of chemical information. The present release of InChl Software v. 1.06 has merged functionality. It allows one to produce both standard and non-standard InChlKey.

II. ABOUT InCh! PROGRAMS

This document is accompanied by version 1.06 of the InChI generator executable. This program runs under 32/64 bit Microsoft Windows (inchi-1.exe) and Linux (inchi-1) operating systems. Also included is winchi-1.exe, a convenient Windows graphical-interface application.

As structure input, the programs currently accept standard SDfiles, Molfiles [see "Description of several chemical structure file formats used by computer programs developed at Molecular Design Limited" by Arthur Dalby, James G. Nourse, W. Douglas Hounshell, Ann K. I. Gushurst, David L. Grier, Burton A. Leland, and John Laufer, Journal of Chemical Information and Computer Sciences, 1992; 32(3); pp. 244-255]; a more recent description of V2000 and the latest V3000 formats may be downloaded from [http://accelrys.com/products/collaborative-science/biovia-draw/ctfile-no-fee.html], or its own output produced when the "Full auxiliary information" option is selected. Input may originate from individual disk files or through the Windows clipboard. From v. 1.05, a limited support of V3000 Molfiles is included.

InChI may be also generated by using Software Library/application programming interface (API). This is described later.

III. RUNNING Inchi PROGRAMS

Command Line Executable inchi-1

An executable program (inchi-1.exe under Windows, inchi-1 under Linux) uses command line arguments.

Full list of available arguments (options) is shown by invoking the program without any arguments.

InChI and InChIKey strings generated by inchi-1 is the reference standard which all other software entities generating InChI/InChIKey should match.

The principal use of the program is batch processing of multiple structure files, primarily SDF files.

Windows version is able of displaying chemical structures, the Linux version does not display structures.

Standard redirection may be used to suppress inchi-1 console output.

Simplistic example of generating InChI and InChIKey under Windows:

```
inchi-1.exe /Key input.sdf
```

under Linux:

```
./inchi-1 -Key input.sdf
```

More advanced example (use advanced v. 1.06 handling of polymers and pseudo atoms, generate 'empty InChl' if error occurs, do not print auxiliary info, write output, log and problem structures to supplied file names):

```
inchi-1.exe /Key /POLYMERS /FOLDCRU /NPZZ /OUTERRINCHI /AUXNONE input.sdf output.txt logfile.log problems.prb \,
```

./inchi-1 -Key -POLYMERS -FOLDCRU -NPZZ -/OUTERRINCHI -AUXNONE input.sdf output.txt logfile.log problems.prb

It is possible to process multiple input files at a single run. This mode is activated by the inchi-1 command line option /AMI (Windows) or -AMI (Linux; AMI stands for "Allow Multiple Inputs"). In this mode, all the file names supplied in the command line are considered as the names of separate input files. For further convenience, the common file name wildcards ("*" and "?") are supported.

For example, issuing a command inchi-1 *.mol /AMI (Windows) or inchi-1 *.mol -AMI (Linux) will instruct the executable to process all the MOL files in the current directory.

Note, that omitting the switch AMI assumes working in a conventional single-input mode which may result in undesired treatment of wildcards[1].

In AMI mode, the names of output, log and problem files could not be individually specified. Instead, they are formed, for each of multiple inputs, by appending the file name with suffixes ".txt", ".log" and ".prb". However, to partially mimic the behavior of inchi-1 in conventional single-input mode, three additional command line options are introduced (see section "Availability of InChI Software options", Table 4). They allow one to redirect the output to stdout, log to stderr, as well as to suppress creation of problem files.

Examples (Windows, Linux):

```
inchi-1 nci*.mol /AMI /AMIOutStd /AMIPrbNone /AuxNone /Key

./inchi-1 /home/me/mol/nci/*.mol -AMI -AMILogStd -AMIPrbNone
-RecMet -FixedH
```

As indicated by tests, processing of multiple MOL files in AMI mode may be several times faster (the exact speed-up depends on many details; anyway the processing time is still significantly longer than that for a single SDF file containing the same data).

InChI Software since v. 1.05 provides experimental support of InChI/InChIKey for regular single-strand polymers and experimental support of large molecules containing up to 32767 atoms was added.

By default, the executable inchi-1 ignores polymer-specific data (which also ensures compatibility with the behaviour of previous versions); to allow treatment of polymers, one should explicitly use the new command line option <code>Polymers</code> (<code>-Polymers</code> under Linux or <code>/Polymers</code> under Windows). Analogously, switch <code>LargeMolecules</code> is necessary to enable processing molecules having more than 1024 atoms.

Note that support of polymers is an experimental feature. To emphasize this, InChI/InChIKey for a polymer uses the 'B' flag character (for "Beta"), instead of 'S' or 'N' for standard/non-standard InChI. It is supposed that this flag will be replaced by common standard/non-standard conventions if and when InChI for polymers is finally adopted.

Note also that treatment of polymers and the appearance of polymer data in InChI string significantly changed in the current version 1.06. However, compatibility option <code>/Polymers105</code> instructs InChI Software to handle polymers in legacy mode, v. 1.05 (it is planned that this option will be eliminated in future, leaving explicit-pseudo atoms approach the sole mode).

For the full list of enhancements in v. 1.06, please see items "new in v. 1.06" in Table 4 below.

For more details please refer to InChl v. 1.06 Release Notes and InChl Technical manual accompanying this distribution .

InChI Software Library (libinchi)

For advanced users who may want to create the Identifier in their own software the InChI Software Library (InChI API) is provided in a separate package. The package contains 'C' source code for inchi-1.exe, 'C' source code for the InChI Library that may be compiled into a Dynamic Link Library (DLL) libinchi.dll under Windows or Shared Object (SO) libinchi.so under Linux; also, there are 'C' and Python examples of simple applications that read input Molfile and use the InChI Library to produce Identifiers.

The InChI Library does not display structures and is not able to read chemical structural data from the input file. It uses specially formatted input binary data and produces three strings: InChI, the Auxiliary Information, and, if necessary, an error or warning message. Also, there are procedure to calculate InChIKey and other service routines. The source code is accompanied with makefiles tested with gcc under Windows and Linux.

The InChI Library allows one to generate both standard and non-standard InChIs/InChIKeys. For example, an API function GetINCHI() produces standard InChI by default and non-standard InChI if some "InChI creation option" is specified in input parameters. However, for compatibility with the previous v. 1.02-standard (2009) release, the procedures which deal only with stdInChI – for example, GetStdINCHI() - are retained.

The InChI API calls are documented in the separate "InChI API Reference" document.

Graphical Interface Program (winchi-1)


Introduction

Windows graphical program of InChI generation is provided in a 'zip' file INCHI-1-BIN.zip. To

To start the program, run the file winchi-1.exe that was extracted from the zip file.

Generating an InChI begins with the selection of an input structure file. The simplest way is to drag the input structure file from Windows Explorer directory list into the InChI window. Structures also may be copied from certain chemical structure editors (ISIS/Draw with "Copy Mol/Rxnfile to the Clipboard" option or from ACD/ChemSketch) and pasted into the InChI window (Select Edit -> Paste from winchi-1 menu). The input structure file pathname may be provided as a command line option when you start winchi-1. Selection of the input structure file may also be done by first clicking on the 'Open' button (top left corner) and then, in the dialog box that appears selecting a structure file using the '...' button on the right of the 'Input Structure File' field. You may select any of the sample .mol or .sdf files for initial testing. In this dialog you may also enter "Text Header for ID"; this will simply add to the InChI header a structure ID if it is present in an input SDfile (from other input formats the header and ID are extracted automatically).

The result appearing after choosing file "benzoicacid.mol.txt" (contained in examples sub-directory of distribution package: "INCHI-1-TEST\samples\UserGuide\benzoicacid.mol") is presented on Figure 1.



The main output window is composed of two sections: the upper section (shown in white in Figure) shows structural information graphically and the lower section (shown in gray in Figure 1) shows text output.

Upper section

The structure is displayed along with labels generated by InChI algorithms. In cases where an SDF file is input, the first structure shown is the first entry in the input file.

The example shown in Figure 1 is a single component example. If more than one component (independent structure) is found in the first structure file (such as benzoic acid, sodium salt shown in Figure 2), each may be separately examined using the "Choose component" 'combo box' on the upper left of the screen, although they are treated as part of a single compound by InChI (Figures 3 and 4).







Figure 2








The buttons under "Display" permit viewing of the input structure and the preprocessed structure if it differs from the input structure. The buttons under "Options" are the same as in the "Options" dialog box. "Mobile H Perception" removes the "fixed-H" part of the identifier. Figure 6 shows the same structure with the option "Mobile H Perception" off.

On the InChI Toolbar the rightmost box displays the number of sets of equivalent components. When equivalent components are found, they may be highlighted by making a selection in the box. This provides a quick way to determine if two depictions of the same compound are considered to be the same by InChI algorithms, although the actual InChI generated will represent the collection of structures as a single compound.



The structure display shows the canonical identification number of each atom along with the non-stereo equivalence class number assigned to that atom. The canonical number is the unique number given to an atom and used for 'serialization' (creation of the actual InChI). The non-stereo equivalence class number is a number assigned to each set of equivalent atoms (all atoms having the same equivalence class number are indistinguishable, *ignoring stereochemistry*; the equivalence class number is the smallest canonical identification number in the class of equivalent atoms). This information is only intended to assist in the understanding of results of InChI processing and is not directly used in InChI generation except in the processing of stereochemistry.

Stereochemical parities of bonds and atoms are also displayed. A question mark symbol indicates that stereoisomerism is possible, but the configuration has not been specified. Bonds that have been found to be variable by alternation or movement of mobile H-atoms or charges are shown by dotted lines. This information is used only for deciding which bonds may exhibit double bond (*Z/E*) isomerism. By design, the Identifier does not explicitly represent bond types.

Lower Section

The InChI along with auxiliary data and explanatory information is shown in the lower section of the output window. Unlike the graphical display, even if more than one disconnected component is found, all textual results for a single input structure file are shown together. This reflects the important point that all components of a submitted structure are considered by InChI to be part of a single compound. Results for different (disconnected) components of a single substance are separated by semicolons, except for chemical formulas, which, in keeping with common conventions, are separated by dots.

Options

Pressing the Options Button opens the InChI Options Dialog Box.

InChl Options X
Structure Options
☐ Mobile H Perception
✓ Include Stereo:
C From chiral flag
Always include omitted/undefined stereo
☐ Different marks for unknown/undefined stereo
Both ends of wedge point to stereocenters
☐ Include Bonds to Metal
Advanced/experimental
Keto-enol tautomerism
1,5 - tautomerism
☐ Treat polymers
No pre-edits of original polymer structure
Enable CRU folding
☐ Disable CRU frame shift
Allow non-polymer Zz pseudoatoms
Annotation Format (text window only)
Plain Text
Write out/log/problem files to disk
Ignore isotopes in structure display
☑ Display pseudoatoms as stars
OK Cancel
igure 7

The following options are then available (as seen in Figure 7):

- · Mobile H Perception turning Off will fix all H-atoms (disallow H-migration), this allows the generation of a fixed-H section of the Identifier (and makes the resulting InChI non-standard).
- · Include Stereo (Absolute, Relative, Racemic, From chiral flag) include stereo layer and choose its type or exclude all stereo information from the identifier. If the last option is selected then in presence of a chiral flag stereochemistry is considered absolute, otherwise relative.

 For standard InChI the only allowed choice is absolute stereochemistry or omission of all stereo;

other choices make InChI non-standard.

- · Always include omitted/undefined stereo by default, InChI does not include unknown/undefined stereo unless at least one defined stereo is present in the input structure. Turning this option On results in inclusion of unknown/undefined stereo in all cases.
- · Different marks for unknown/undefined stereo turning this option On will result in usage of the two different signs, 'u' and '?', for "unknown" and "undefined" stereo. Briefly: "undefined" means not given while "unknown" means explicitly marked as unknown, e.g., with "wavy" bonds. By default, this option is turned off and the twoh signs are merged to '?' (that is, "unknown" stereo treated as "undefined").
- Both ends of wedge point to stereocenters by default, this option is turned Off. This means that that a stereo bond depicted by a wedge affects the stereochemistry of only the atom 'pointed to' by the narrow end of that wedge. However, it may be turned On if the user is completely sure that a stereobond affects both atoms it connects (that is, for 2D structures complying to the legacy "perspective" stereochemistry drawing style).
- · Include Bonds to Metal turning On will add a layer that includes specific bonding to metals (in case of salts the bonds between a metal and an acid cannot be reconnected as seen in Figures where that choice is "grayed out" and cannot be ticked or checked).
- · Annotation Format (Plain Text; XML, None) choose appropriate format for explanatory information.
- · Ignore Isotopes in Structure Display this does not change the identifier, it only affects the structure appearance and the display of sets of equivalent components.

Note that the above options form a subset of a full options set available in the command-line executable inchi-1 (see section 'InChI Software Options' below).

InChl Software Options

The exact set of InChI Software options has been changing from release to release.

The description below refers to the current v. 1.06.

The options are available in graphical program winchi-1, command line executable inchi-1 and through InChi API. Not all the options are available for all the parts of software; the maximal set of options is available for the inchi-1 program.

Options affecting generation of InChI are divided on "structure perception" options and "InChI creation" options.

The perception options are considered drawing style/edit flags which affect the input structure interpretation and are not memorized. It is assumed that the user may deliberately use these options to account for the specific features of structure collections. Whence, perception options may be used while generating standard InChI without loss of its "standardness".

Perception options are listed in the following tables. Presented here are command line switches available (they should be used with the appropriate prefix - i.e., NEWPSOFF should be entered as /NEWPSOFF under Windows and -NEWPSOFF under Linux).

Table 1. Structure perception options.

Structure perception option	Meaning	Default behavior (standard; if no option supplied)
NEWPSOFF	Both ends of a wedge (which indicates stereochemistry) point to stereocenters	Only the narrow end of a wedge points to a stereocenter
DoNotAddH	All hydrogens in input structure are explicit	Add H according to usual valences
SNon	Ignore stereo	Use absolute stereo

There are several options (Table 2) which modify the interpretation of input stereochemical data. In principle, they also may be considered "structure perception" options. However, as the standard InChI, by definition, requires the use of absolute stereo (or no stereo at all), these "perception" options assume generation of non-standard InChI.

Table 2. Stereo interpretation options (lead to generation of non-standard InChI).

Stereo option	Meaning	Default behavior (standard; if no option supplied)	
SRel	Use relative stereo	Use absolute stereo	
SRac	Use racemic stereo	Use absolute stereo	
SUCF	Use Chiral Flag in MOL/SD file record: if On – use absolute stereo, Off – relative	Use absolute stereo (or another option if requested by SRel /SRac/SNon switches)	

The creation options affects the InChI algorithm, not structure perception. They modify the defaults which are specified for standard InChI and significantly affect the final appearance (e.g., additional InChI layers may appear). Whence, using any of the creation options qualifies the resulting identifier as non-standard.

Creation options used for generation of a particular non-standard InChI may be appended to the created identifier, see below.

InChI creation options are listed in the following table.

InChl creation option	Meaning	Default behavior (if no option supplied)	
SUU	Always indicate unknown/undefined stereo	Does not indicate unknown/undefined stereo unless at least one defined stereocenter is present	
SLUUD	Stereo labels for "unknown" and "undefined" are different, 'u' and '?', resp. (new option; see explanation)	Stereo labels for "unknown" and "undefined" are the same ('?')	
RecMet	Include reconnected metals results	Do not include	
FixedH	Include Fixed H layer	Do not include	
KET	Account for keto-enol tautomerism (experimental extension to InChl v. 1)	Ignore keto-enol tautomerism	
15T	Account for 1,5-tautomerism (experimental extension to InChl v. 1)	Ignore 1,5-tautomerism	
LargeMolecules	Accept molecules containing more than 1024 (but less than 32767) atoms	Reject molecules containing more than 1024 atoms	
Polymers	Accept polymer data in input V2000 Molfiles.	Ignore polymer data in input V2000 Molfiles.	
OutErrInChI	Output empty InChI and corresponding InChIKey if error occurs	Output nothing	

The standard InChI is always generated if no InChI creation/stereo modification options are specified. This means:

- · include tautomerism (i.e., turn mobile H perception on, exclude "fixed hydrogen atoms" layer) except for keto-enol and 1,5-tautomerism;
- · omit reconnection of bonds to metal atoms;
- · only the narrow end of a wedge points to a stereocenter;
- · exclude unknown/undefined stereo if no other stereo is present;
- · treat stereochemistry as absolute (not relative or racemic).

Inversely, if any of SUU/SLUUD/RecMet/FixedH/Ket/15T/SRel/SRac/SUCF options are specified in the command line, the generated InChI will be non-standard.

Since the software v. 1.03, the command-line option SaveOpt was introduced to append saved InChI creation options to a non-standard InChI string.

Since v. 1.06, this option is deprecated.

It is still retained for compatibility reasons, but no further development is planned. For the

SaveOpt details, please consult InChI Software User Guide of v. 1.05 (2017) available at https://www.inchi-trust.org/downloads/

The next table summarizes the current, v. 1.06, availability of various options in the various parts of the InChI Software.

Table 4. Availability of InChI Software options (note entries marked "new in v. 1.06).

Options availability				
winchi	inchi-	API calls	Option (without / or – prefix)	Explanation
Input				
-	Yes	-	STDIO	Use standard input/output streams
-	Yes	-	InpAux	Input structures in InChI default aux. info format (for use with STDIO)
Yes	Yes	Yes	SDF:name	Read from the input SDfile the ID under the named data header
-	Yes	-	AMI	Allow multiple input files
-	Yes	-	START:number	Start from SDF record number
-	Yes	-	END:number	End at SDF record <i>number</i>
-	Yes	-	RECORD:number	process only SDF record number

Options availability				
Output				
-	Yes	Yes	AuxNone	Do not produce Auxiliary Information
-	Yes	-	NoLabels	Omit structure number, DataHeader and ID from InChl output
-	Yes	Yes	NoInChI	(new in v. 1.06) Do not print InChI string itself
-	Yes	Yes	SaveOpt	(deprecated since v. 1.06) Save custom InChl creation options
-	Yes	-	Tabbed	Separate structure number, InChl, and AuxIndo with tabs
-	Yes	Yes	NoWarnings	(new in v. 1.06) Suppress all warning messages(default: show)
-	Yes	-	OutErrInChI	On fail, print empty InChI (default: nothing)
Always	Yes	-	D	Display the structure
-	Yes	Yes	OutputSDF	Convert InChI created with default auxiliary info to a SDfile
-	Yes	Yes	SdfAtomsDT	Output Hydrogen Isotopes to SDfile as Atoms D and T
-	Yes	-	AMIOutStd	Write output to stdout (in AMI mode only)
-	Yes	-	AMILogStd	Write log messages to stderr (in AMI mode only)

Options availability				
-	Yes	-	AMIPrbNone	Suppress creation of problem files (in AMI mode only)
Structure perception				
Yes	Yes	Yes	NEWPSOFF	Both ends of wedge point to stereocenters
-	Yes	Yes	DoNotAddH	Do not add H according to usual valences
Yes	Yes	Yes	SNon	Ignore stereo information in input structures
-	Yes	Yes	LooseTSACheck	(new in v. 1.06) Relax criteria of ambiguous drawing for in-ring tetrahedral stereo
Stereo perception modifiers (non- standard InChl)				
Yes	Yes	Yes	SRel	Relative stereo
Yes	Yes	Yes	SRac	Racemic stereo
Yes	Yes	Yes	SUCF	Use Chiral Flag: On means Absolute stereo, Off - Relative
Customizing InChI creation (non-standard InChI, "InChI=1/")				
Yes	Yes	Yes	SUU	Always include omitted unknown/undefined stereo
Yes	Yes	Yes	SLUUD	Make labels for unknown and undefined stereo different
Yes	Yes	Yes	RecMet	Include reconnected metals results

Options availability				
Yes	Yes	Yes	FixedH	Include Fixed H layer
Experimental (InChI=1/B")				
Yes	Yes	Yes	KET	Account for keto- enol tautomerism (experimental)
Yes	Yes	Yes	15T	Account for 1,5- tautomerism (experimental)
Always	Yes	Yes	LargeMolecules	Experimental support of molecules up to 32767 atoms
Yes	Yes	Yes	Polymers	Experimental support of simple polymers
Yes	Yes	Yes	Polymers105	(new in v. 1.06) Experimental support of simple polymers in older v. 1.05 way
Yes	Yes	Yes	FoldCRU	(new in v. 1.06) Fold polymer CRU if inner repeats occur
Yes	Yes	Yes	NoFrameShift	(new in v. 1.06) Disable polymer CRU frame shift
Yes	Yes	Yes	NPZz	(new in v. 1.06) Allow non-polymer Zz (pseudo element) atoms
-	Yes	Yes	SAtZz	(new in v. 1.06) Enable stereo at atoms connected to Zz pseudo atoms (default: disable/ignore)
Generation				
- (always 60)	Yes *)	Yes*)	Wnumber	Set time-out per structure to <i>number</i> seconds

Options availability				
- (always 60000)	Yes *)	Yes*)	WMnumber	(new in v. 1.06) Set time-out per structure to number milliseconds
-	Yes	Yes	WarnOnEmptyStructure	Warn and produce empty lnChl for empty structure
Always	Yes	- **)	Key	Generate InChlKey
Always	Yes	- **)	XHash1	Generate hash extension (to 256 bits) for 1st block of InChlKey
Always	Yes	- **)	XHash2	Generate hash extension (to 256 bits) for 2nd block of InChlKey
-	Yes	-	MergeHash	(new in v. 1.06) On output, combine InChIKey with extra hash(es)
Conversion				
-	Yes	-	InChl2Struct	Convert standard InChl string(s) into structure(s)

^{*)} W0 means unlimited time. In InChI Library the default is W0, in inchi-1 the default is 60 seconds (W60).

IV. CHEMICAL STRUCTURE INPUT

Molfile structures may be submitted either as a single Molfile or as a series of concatenated Molfiles (an SDfile). A number of programs, some of them freely available, may be used to create these Molfiles. Information on how to produce and convert If an input structure contains more than one independent structure, each component is individually shown in the graphical output section of the program, though this has no effect on the InChI. Text results are given for all layers and all components (different components of a single substance are separated by semicolons in each layer, except for chemical formulas, which, by convention, are separated by dots.).

^{**)} In InChI Library, generation of InChIKey/hash extensions is performed via a separate API call.

While structure normalization methods built into the program perceive a range of different structure drawing conventions, it is possible that other conventions may not be properly recognized. Examination of the graphical results of InChI processing, especially for equivalent atom classes and stereo labeling, should reveal such problems.

If an SDfile is 'labeled', the program can supply these labels in its output. If the tag name is 'Name' and the data field is '2-methylanthracene', this information would appear in the SDfile as 3 lines (the last line is blank):

>

2-methylanthracene

In this case, if the tag 'Name' is entered in the 'Structure ID Header' field in the input dialog box, '2-methylanthracene' will appear in the output text.

A variety of structure files are provided for testing. Individual Molfiles have extension .MOL, concatenated Molfiles have extension .SDF.

Since v. 1.05, the ability to read and parse large (up to 32767 atoms) input files in Molfile V3000 format was added to the inchi-1 executable and the API procedure MakeINCHIFromMolfileText(). This is necessary for treating large molecules (previous versions supported only V2000 format limited to not more than 1000 atoms).

In addition, provisional support for extended features of Molfile V3000 was also added, both to inchi-1 and the InChI Software Library, API. This means that extended data (on haptic coordination bonds and stereo collections) are read and parsed; however, they are not used currently (as this requires significant modification of the Identifier itself, not just the Software).

InChI Software has experimental support of regular single-strand polymers. Both structure-based and source-based representation and encoding of polymers are supported.

Executable inchi-1 supports reading input Molfile files containing polymer description lines. This support is also built into several API procedures (see "API Reference" document of this distribution).

Test Files

A number of Molfiles (.mol) and SDfiles (.sdf) are included with this distribution for illustrative purposes. In particular, file samples_UserGuide.zip contains MOL files for the examples used in this document.

V. Further reading and contacts

In addition to this introductory User Guide, a number of materials concerning InChI is currently available.

In particular, this distribution contains separate documents (PDF files) with InChI Technical Manual (InChI_TechMan.pdf) and InChI API Reference (InChI_API_Reference.pdf). For more brief and less technical description, look at: *Heller, S., McNaught, A., Pletnev, I., Stein, S., and Tchekhovskoi, D. InChI, the IUPAC international chemical identifier. Journal of Cheminformatics 7 (2015), 23–23.* DOI: 10.1186/s13321-015-0068-4 For much more brief description, as well as for background and history, look at: *Heller, S., McNaught, A., Stein, S., Tchekhovskoi, D., and Pletnev, I. InChI - the worldwide chemical structure identifier standard. Journal of Cheminformatics 5 (2013), 7–7.* DOI: 10.1186/1758-2946-5-7

For InChI FAQ, address to: http://www.inchi-trust.org/technical-faq/

Contacts:

Richard Kidd,
InChl Trust,
c/o Cambridge Crystallographic Data Centre, 12 Union Road, Cambridge, UK CB2 1EZ
richard@inchi-trust.org

Steve Heller (InChl project director, InChl Trust) steve@hellers.com

Igor V. Pletnev (InChl developer) igor.pletnev@gmail.com